GENERAL

how to start windows in safe mode

Published: September 3, 2026 | Index ID: #-

How to Start Windows in Safe Mode: A Step by Step Guide

Ever find yourself staring at a blinking cursor, a blue screen, or a Windows error that refuses to let you log in? You're not alone. Whether it's a stubborn driver conflict, a malware infection, or a recent update that went wrong, Windows Safe Mode can be your lifeline. Safe Mode boots Windows with only the essential files and drivers, allowing you to troubleshoot, clean up, and restore your system without the interference of third party software.

In this guide we'll walk you through every method you can use to start Windows in Safe Mode, explain why it's useful, and give you practical tips for getting the most out of this powerful diagnostic tool. By the end, you'll know how to launch Safe Mode on Windows 10, Windows 11, and older versions, and how to use it to solve a wide range of problems.

What Is Safe Mode?

Safe Mode is a diagnostic startup option that loads only the core components required for Windows to operate. This includes a minimal set of drivers and services, excluding most third party software, visual effects, and non essential hardware drivers. The result is a lightweight, stable environment that makes it easier to identify and fix issues that would otherwise prevent normal boot.

Key Features of Safe Mode

- Minimal Driver Set: Only essential drivers are loaded.
- No Third Party Services: Background programs and services are disabled.
- Limited Functionality: Many features (e.g., networking) are disabled by default, but can be enabled if needed.
- Safe for Malware Removal: Many malware strains cannot run in Safe Mode, making removal easier.

Why Use Safe Mode?

Safe Mode is invaluable when:

- Windows fails to boot normally.
- Recent updates or driver installations cause instability.
- Malware or viruses are suspected.
- Hardware conflicts need diagnosing.
- You need to uninstall or update drivers that are causing problems.

Because Safe Mode runs with a clean slate, you can safely perform actions like uninstalling problematic software, updating drivers, or scanning for malware without interference.

Methods to Start Windows in Safe Mode

Below are the most common ways to boot Windows into Safe Mode. Choose the one that best fits your situation.

1. Using the Shift /+ /Restart Menu (Windows /10 & /11)

1. Click the Start button, then the power icon.
2. Press and hold the Shift key while selecting Restart.

3. Windows will reboot into the Choose an option screen.
4. Select Troubleshoot /!' /Advanced options /!' /Startup Settings.
5. Click Restart again.
6. After the restart, press 4 (or F4) for Safe Mode or 5 (or F5) for Safe Mode with Networking.

2. Using the F8 Key (Older Windows Versions)

On Windows 7 and earlier, you can press **F8** repeatedly right after the BIOS screen to bring up the **Advanced Boot Options** menu.

1. Restart your computer.
2. Immediately press F8 repeatedly.
3. When the menu appears, use the arrow keys to select Safe Mode or Safe Mode with Networking.
4. Press Enter to boot.

Note: In Windows 8 and later, the F8 method is no longer reliable due to faster boot times. Use the Shift + Restart method instead.

3. Using System Configuration (msconfig)

1. Press Win /+ /R to open the Run dialog.
2. Type msconfig and hit Enter.
3. Navigate to the Boot tab.
4. Under Boot options, check Safe boot and choose Minimal (Safe Mode) or Network (Safe Mode with Networking).
5. Click Apply then OK.
6. Restart your computer; it will boot into Safe Mode.
7. After you're done troubleshooting, open msconfig again, uncheck Safe boot, and reboot normally.

4. Using a Recovery Drive or Installation Media

1. Insert your Windows recovery drive or installation USB/DVD.
2. Restart and boot from the media (you may need to change the boot order in BIOS).
3. Choose your language preferences, then click Next.
4. Select Repair your computer instead of Install now.
5. Navigate to Troubleshoot /!' /Advanced options /!' /Startup Settings and click Restart.
6. After the reboot, press 4 or 5 to select Safe Mode.

5. Using Command Prompt (bcdedit)

If you can boot into Windows normally, you can enable Safe Mode via the command line.

1. Open Command Prompt as an administrator.
2. Enter the following command to enable Safe Mode with Networking:

```
bcdedit /set {default} safeboot network
```

1. Restart your computer; it will boot into Safe Mode.
2. To disable Safe Mode, run:

```
bcdedit /deletevalue {default} safeboot
```

6. Using Windows Settings (Windows /10/11)

1. Open Settings (Win /+ /I).
2. Go to Update & Security /!' /Recovery.
3. Under Advanced startup, click Restart now.

4. After the restart, follow the same steps as in the Shift /+ /Restart method (Troubleshoot !’ Advanced options !’ Startup Settings).

Tips for Safe Mode Success

- Backup First: If possible, create a system image or backup important files before making changes.
- Keep It Short: Once you’re in Safe Mode, perform only the necessary actions and exit promptly to return to normal mode.
- Enable Networking If Needed: Use Safe Mode with Networking if you need internet access for driver downloads or updates.
- Use Built in Tools: Run msconfig, Device Manager, or Event Viewer from Safe Mode to diagnose issues.

What to Do Once in Safe Mode

Here are some common tasks you can perform safely when Windows is in Safe Mode.

Uninstall Problematic Software

Malware, buggy drivers, or recently installed programs can cause crashes. Open **Control Panel /!’ /Programs /!’ /Uninstall a program** and remove any suspicious or recently added applications.

Update Drivers

Faulty or outdated drivers are a frequent culprit. In Safe Mode, open **Device Manager**, right click a device, and choose **Update driver**. You can also use the manufacturer’s website to download the latest driver versions.

Run Antivirus Scans

Many antivirus programs don’t run in Safe Mode. Instead, download a reputable **portable antivirus scanner** (e.g., Malwarebytes, Bitdefender Rescue Disk) and run it from a USB drive.

Check Disk for Errors

Run a disk check to find and fix file system errors. Open Command Prompt as administrator and type:

```
chkdsk C: /f /r /x
```

Replace **C:** with the appropriate drive letter if your system partition is different.

Use System Restore

If you have a restore point from before the problem began, you can revert your system. In Safe Mode, go to **Control Panel /!’ /Recovery /!’ /Open System Restore** and follow the wizard.

Exiting Safe Mode

Once you’ve finished troubleshooting, simply restart your computer. Windows will boot normally unless you left the Safe Mode setting enabled (e.g., via **msconfig** or **bcdedit**). If you used **msconfig**, remember to uncheck **Safe boot** before rebooting. For **bcdedit** users, run the delete command again as shown earlier.

Common Issues & Troubleshooting

- Safe Mode Doesn’t Appear: If the Advanced Boot Options menu is missing, try the Shift /+ /Restart method or create a recovery drive.
- Unable to Access Internet in Safe Mode: Select Safe Mode with Networking or manually enable networking through the Network Connections panel.

- Boot Loop After Safe Mode: If Windows keeps restarting in Safe Mode, it may indicate a deeper system issue. Use the Repair your computer option from recovery media to run startup repair.
- Hardware Not Detected: Some hardware (e.g., Wi Fi adapters) may not function in Safe Mode. Install drivers manually or use Safe Mode with Networking to download them.

Final Thoughts

Baca Juga (Artikel Terkait)

- **automaker mini software version v8 erptoboss**
  URL: http://www.dtrainderailed.com/automaker-mini-software-version-v8-erptoboss.pdf
- **automata and computability**
  URL: http://www.dtrainderailed.com/automata-and-computability.pdf
- **automata and languages theory and applications**
  URL: http://www.dtrainderailed.com/automata-and-languages-theory-and-applications.pdf
- **automata and mechanical toys**
  URL: http://www.dtrainderailed.com/automata-and-mechanical-toys.pdf

Tags: #start #windows #safe #mode